
Gmail app set up

Note: Most Android devices have a default Gmail app installed. To connect the default Gmail app, use the following settings:

1. Select Exchange > click Next.



2. Type in your primary email address and your password.


Note: If you have an Autodiscover record compatible with Exchange server set up, tap **Next**, and your email account will set up automatically.

If the settings are populated incorrectly or you do not have that record, tap **Manual setup**.



- 3. Type in the settings. You can find all the settings here:
 - o **Username:** Type in your primary email address.
 - o **Password**: Mailbox password.
 - o Client certificate: None.
 - o **Server Name:** Type in the correct Server Name.
 - o **Port:** 443
 - Use Secure connection: SSL/TLS


Click Next.



4. Accept the security prompt.



5. Change synchronization scope (YOUR COMPANY does not recommend to synchronize all the data for big mailboxes).



- 6. Set the account as default one if you want it to be your reply from the account.
- 7. Provide the description for the account (optional).
- 8. Finish the setup by tapping on **Next** button.
- 9. Finished!

On some Android devices there are <u>only two fields for setting up an</u> <u>Exchange account</u>: *Email address* and *Password*. Use the following settings to set up the account:

- Email address
- Password: your mailbox password
- Tap Add Account
- Enter the Server address in the new field that will appear and change the
 Email address field to your primary email address. Tap Next to finish the setup.

Note: if the 'Cannot connect to the server' error comes up during configuration, try to switch from Wi-Fi to your mobile network or vice versa.



Native app set up

Below you will find the instructions to connect native app for some Android devices to Exchange server:

Samsung HTC

Samsung


1. On the Home Screen of your device tap the **Menu** button and choose **Settings**.



- 2. Tap Add Account.
- 3. Choose Microsoft Exchange ActiveSync.
- 4. Type in your primary email address and your password.

Note: If you have an Autodiscover record compatible with Exchange server set up, tap **Next**, and your email account settings automatically. If the settings are populated incorrectly or you do not have that record, tap **Manual setup**, next page.





Click "Manual Setup."



- 5. Type in the following settings:
 - o **Email address:** Type in your email address.
 - Domain\Username: Type in EXCH domain\Canonical user name.
 Note: Please contact ImageQuest for this information
 - Password: Mailbox password.
 - o **Exchange server:** Type in the correct Server Name.
 - Use Secure connection (SSL): Checked.
 - Use client certificate: Not checked.



- 6. Click Next.
- 7. Accept the security prompt.
- 8. Finished!




HTC

1. From the Home Screen select **Settings**.




- 2. Choose Accounts & sync > select Add Account option.
- 3. Choose Exchange ActiveSync for HTC.
- 4. Type in your primary email address and your password.

Note: If you have an Autodiscover record compatible with Exchange server set up, tap **Next**, and your email account will set up automatically. If the settings are populated incorrectly or you do not have that record, tap **Manual setup** and follow the directions on the next page.





- 5. Type in the following settings:
 - o **Domain:** leave the field blank
 - Username: type in your primary email address.
 - o **Password**: mailbox password.
 - Server Name: type in the correct Server Name.
 - Use Secure connection (SSL): checked.



- 6. Click Next.
- 7. Accept the security prompt.
- 8. Finished!

